
ANDROID DEVICE EMAIL SETUP


If this is the first email account you're setting up on your ANDROID DEVICE, follow the guide below.



STEP 1: Main Screen

On the Main screen, [TOUCH] "Email".

STEP 2 : Setup Email (Manual)



Enter your account information using your keypad.


ENTER: "Your login username".

(Usually it is your email address)

ENTER: "Your account password.".

[TOUCH] "Manual setup".

STEP 3 : Account type



[TOUCH] "POP3 account".

STEP 4 : Incoming server settings



Enter your incoming server information using your keypad.

Username: [ENTER] "Your login username".

(Usually it is your email address)

Password: [ENTER] "Your account password.".

POP3 Server: [ENTER] "mail.yourdomain.com".

(yourdomain.com here refers to the domain you have

registered)

Security type: [ENTER] "None."

Port: [ENTER] "110."

Delete email fro: [REMAIN AS] "Never." server

[TOUCH] "Next".

STEP 5 : Outgoing server settings



Enter your outgoing server information using your keypad.

SMTP server: [ENTER] "mail.yourdomain.com".

(yourdomain.com here refers to the domain you have registered)

Security type: [ENTER] "None."

Port: [ENTER] "25."

Require sign-in: [ENABLE]


Username: [ENTER] "Your login username".

(Usually it is your email address)

Password: [ENTER] "Your account password.".

[TOUCH] "Next".


STEP 6 : Account options



Select the options according to your requirement.

[TOUCH] "Next".

STEP 7 : Set up email



Enter the final information to your account using your keypad.


Give this account a name: [ENTER] "Your email address".

(Optional) (This is the easiest way to differentiate between accounts

if you have more than 1)

Your name: [ENTER] "Your name as you want it to display on email messages."

[TOUCH] "Done".



The setup is now completed.

You will now be brought to your account "Inbox" and you will see your emails start to appear (if you do have emails).

How do I find the server settings?

To find your server settings, sign in to your email account using Outlook . After you sign in, click **Options** > **See All Options** > **Account** > **My Account** > **Settings for POP, IMAP and SMTP access**. The POP3, IMAP4, and SMTP server name and other settings you may need to enter are listed on page under **POP setting** or **IMAP**setting and **SMTP setting**.